

The installation & Updating of DPNet PCI drivers in Windows

Important

Cannot be used with 64-Bit versions of Windows as there are **NO** 64bit Drivers !



Install card into PC then power up PC and follow instruction on following pages

Installing Drivers

Windows 7 Drivers see page 2

Windows Vista (XP) See page 6

Checking Version installed See page 9

Uninstalling / Updating Drivers



Win 7 / Vista Uninstalling / Updating See Page 10

Win XP Uninstalling / Updating See Page 11

Windows 7

When interface is installed and the PC is switched on Win 7 will search drivers but does not give you an option to browse the Dairyplan CD

This means Drivers will have to be installed manually




1 Click start


2 Type 'Device manager'

3 Click on Device Manager


Device Manager will appear




4 Click on the arrow by Other Devices



5 Right Click on Network adaptor or unkown device



6 Click on Update Driver Software



Important You must install Driver version 2.2.0.0

These are only found on
DP5.240-178 CD or later
Note they are also on the UK Info DVD (since April 2011)


Browse to the driver folder on Dairyplan CD, the path is \\Driver\DPNET\XLON-PCI

(note older DP5 and C21 disks do not have good drivers on them)



9

Click Install this driver software anyway




10

Click Close

Windows Vista (XP Is Similar)


1

Click Here




2

Click Continue




3

Click Here




Click Here

4



5

Click Browse




Using Dairyplan 5.2 CD (use XP driver currently)
V2.2 driver also on the UK Info DVD (since April 2011)

6

browse to the folder \Driver\DPNET\XLON-PCI





7

Click Install this driver software anyway

8

Click Close

Check the version is at least 2.2.0.0

Open Windows Device manager




Right Click on Xlon PCI

then click on Properties give this screen

Click on Driver

See Driver version Number



Updating Drivers Guide

To update the Xlon-PCI drivers first you must remove the old Drivers as just updating does not guarantee Windows will use the newer Driver

For Windows Vista & Window 7 this can be done directly from Windows device manager
For Windows XP the 3 driver files have to be manually Deleted unding Windows Explorer

Windows Vista & Window 7 un-instating drivers

- 1] First take Backup of Dairyplan
- 2] Close DPProcesscontrol
- 3] Open Windows Device manager



Right Click on Xlon PCI

click on Uninstall gives this screen

Important Tick the box Delete the Driver

Then Click OK

Finally restart PC and follow instruction for installing V2.2 Drivers



Updating Drivers Guide XP

Windows XP un-instating drivers

- 1] First take Backup of Dairyplan
- 2] Close DPProcesscontrol
- 3] Open Windows Device manager



Right Click on Xlon PCI

click on Uninstall gives this screen

Then Click OK



Then using Windows Explorer find these 3 file in the C:-Drive and Delete Them

C:\Windows\System32\Driver\xlonpci2.sys

C:\Windows\System32\xlonutil.dll

C:\Windows\System32\xlonpp2.dll

Finally restart PC and follow instruction for installing V2.2 Drivers